

# BONNET CLEANING – SPRAY METHOD

## Tools Needed

- Wet Floor Sign
- 175 – 300 RPM Floor Machine with Bonnet Holder
- Bonnet Pads (2 minimum, more depending upon size of room)
- 1 gallon sprayer
- Measuring Cup

## Product Needed

P&G Pro Line  
Bonnet / Traffic Lane Cleaner



**FREQUENCY OF CLEANING:** Weekly or monthly to clean top fiber sections of carpet. Carpet will look slightly soiled from oily soils attached to top portion of carpet fibers.

**PREPARATION:** Collect all tools, equipment and products required. Ensure all equipment is operational. Review MSDS, product labels and caution statements. Choose appropriate safety equipment.

**SPECIAL DIRECTIONS FOR THIS TASK:** Pre-test bonnet cleaner for colorfastness before use. Do not use if color is removed, faded or otherwise changed. Clear furnishings from area. Protect furnishings that cannot be moved. Replace furnishings when finished. Use furniture pads if furniture must be replaced before floor is dry. When finished, clean and return equipment to storage area.



**NOTE:** Pre-test cleaner for colorfastness before use. Do not use if color is removed faded or otherwise changed.

### STEP 1

- Pre-treat spots and remove chewing gum following the Carpet Spot Removal Procedure.
- Remove loose soil by following the Vacuum Procedure. It is critical to vacuum well before doing any wet carpet cleaning.





### STEP 2

- Post "out of service" sign in area to be cleaned.




### STEP 3

- Dilute P&G Pro Line Bonnet / Traffic Lane Cleaner at 1:8 (1 part concentrate to 8 parts water).
- In order to fill a 1 gallon sprayer at 1:8 dilution, follow these steps to insure good mixing and reduce foaming during mixing:
  - Fill 1 gallon sprayer with water until level reaches about ½ full.
  - Add 14 ounces of traffic lane/bonnet cleaner.
  - Slowly add water until solution level reaches the 1 gallon fill line.



### STEP 4


- Start at farthest point from door, working in a 10 ft. by 10 ft. area.
- Hold spray nozzle 12 inches from carpet.
- Apply solution in even, overlapping strokes on localized traffic lane and other highly soiled localized areas.
- Lightly apply solution to bonnet.
- Buff area, moving machine left to right, overlapping each pass..



**NOTE:** Turn bonnet pad over as the pad becomes soiled. Replace with clean bonnet as needed.

### STEP 5

- Move to next 10 ft. by 10 ft. area, working towards doorway and repeat Step 3 through Step 4.



**NOTE:** To speed dry carpet, buff with clean dry bonnets, turning and changing often. A fan may be used. Direct air movement across or out from room.

### STEP 6

- Vacuum carpet when dry following the Vacuum Procedure.

